

SOLID MIX SERIES

SOLID BUS COMP



Manual



The information in this document is subject to change without notice and does not represent a commitment on the part of Native Instruments GmbH. The software described by this document is subject to a License Agreement and may not be copied to other media. No part of this publication may be copied, reproduced or otherwise transmitted or recorded, for any purpose, without prior written permission by Native Instruments GmbH, hereinafter referred to as Native Instruments.

“Native Instruments”, “NI” and associated logos are (registered) trademarks of Native Instruments GmbH.

Mac, Mac OS, GarageBand, Logic, iTunes and iPod are registered trademarks of Apple Inc., registered in the U.S. and other countries.

Windows, Windows Vista and DirectSound are registered trademarks of Microsoft Corporation in the United States and/or other countries.

All other trade marks are the property of their respective owners and use of them does not imply any affiliation with or endorsement by them.

Document authored by: Nicolas Sidi

Document version: 1.0 (08/2011)

Special thanks to the Beta Test Team, who were invaluable not just in tracking down bugs, but in making this a better product.

Germany

Native Instruments GmbH
Schlesische Str. 29-30
D-10997 Berlin
Germany
www.native-instruments.de

USA

Native Instruments North America, Inc.
6725 Sunset Boulevard
5th Floor
Los Angeles, CA 90028
USA
www.native-instruments.com



© Native Instruments GmbH, 2011. All rights reserved.

Table of Contents

- 1 Introduction 5**
 - 1.1 What Is a Compressor? 5
 - 1.1.1 Main Compression Parameters 6
 - 1.1.2 Other Compression Parameters and Features 6
 - 1.1.3 What Is a Bus Compressor? 7
 - 1.2 The SOLID BUS COMP 7
- 2 Using the SOLID BUS COMP 9**
 - 2.1 Loading the SOLID BUS COMP 9
 - 2.2 SOLID BUS COMP Interface and Controls 10

1 Introduction

SOLID BUS COMP brings the stereo bus compressor of one of the most renowned studio mixing consoles of all times into the Rack of GUITAR RIG 5.

1.1 What Is a Compressor?

Technically speaking, a compressor is an audio processing unit that reduces the dynamic range of an incoming signal, i.e. reduces the level difference between the signal's quiet and loud sections. This way, it can help to increase the perceived loudness of a signal and attract the listener's attention.

For many studio and live music applications, the usage of compressors is inevitable: they let you “glue” the individual instruments of an instrument group together and make them “sit” in the mix more naturally, which is particularly helpful when mixing drum recordings. Compression can also stretch the decay phase of instruments, mostly drums, and add sustain to the tone of electric guitars.

However, compression can be used for a wide range of applications. Here are a just few examples:

- Electric guitars and basses: Compression is applied to picked string instruments in order to smooth the varying intensity of the individual strokes, thus increasing the perceived overall level. At extreme settings, you can get a “wall-of-sound” effect!
- Drums: Adding compression to a bass drum or snare track will add punch and help define its sound in your mix.
- Vocals: Adding compression to vocals can make them sound more balanced by leveling the soft and loud sounds in the voice.
- Mixing/pre-mastering: A slight compression applied to the overall mix (or some specific subgroups) can add cohesion between the various instruments.

Using compression is a fine art: You can easily destroy your sound if you don't carefully set the compression parameters! For each purpose, specific settings are required. A good understanding of each parameter's effect, together with experience gained by using the compressor, will allow you to achieve great results!

In addition to the above listed common applications there is room for your own experiments, so feel free to use your compressor in a way not listed here.

1.1.1 Main Compression Parameters

Compression can be controlled by several parameters. The most important parameters are the following:

- The **threshold** defines the audio level above which compression takes place. Below this threshold level, the incoming signal is left untouched; above this threshold level, the gain of the incoming signal is attenuated.
- You can choose how much attenuation is applied to the signal by defining an input/output **ratio**. For example, when you select a ratio of 2:1, an input level that is 2 dB above the threshold will create an output level that is only 1 dB above the threshold.



By setting an extreme compression ratio, you can practically prevent the signal from exceeding the threshold level. The compressor then acts as a limiter.

- Since the compression attenuates the higher levels of your input signal, most compressors allow you to add a fixed **make-up gain** to the output in order to counterbalance the loss of level.

1.1.2 Other Compression Parameters and Features

The compression process can be further tuned by using additional parameters and features.

Attack and Release

The **attack time** can define how long it takes for the compressor to come into full effect when the threshold level is reached. For example, a longer attack time can be useful to retain the attack transients on a percussive or plucked string instrument in order to only compress the instrument sound coming after the transients. For this, you could also make use of parallel compression (see below).

Similarly, the **release time** can define how long it takes for the active compressor to return to its standby state after the signal level has fallen below the threshold level.

The right settings for attack and release time strongly depend on both the current purpose of the compression and the kind of instrument that you are working on!

Side Chain Input

Every compressor uses a detector to decide when to kick in. This detector listens to a control signal and activates the compressor when needed.

Usually, the detector listens to the input signal itself and activates the compressor whenever the level of the input signal exceeds the selected threshold.

A **side chain input**, on the contrary, allows you to feed the detector with another signal (e.g. another track in your mix). In this setup, compression is applied according to the level of the other signal. This greatly widens the versatility of your compressor.



Typically the side chain input is fed by the bass drum track as a control signal to trigger the compressor on the bass guitar track. Another example is the “auto talk over” feature found on several mixers, which automatically attenuates the level of the music as soon as you talk into the microphone.

Parallel Compression

Sometimes you may want to keep the original signal and blend it with the compressed signal. Setting up a signal path for **parallel compression** can help retain some of the sonic characteristics of your original instrument (mainly the transients) when a signal is heavily compressed and in need of some top-end sparkle.

1.1.3 What Is a Bus Compressor?

A bus compressor is nothing else than a compressor meant to be used on a bus (also called “group” or “subgroup” on some devices) — in other terms, on a group of channels. For example, this can be the case when mixing drums, where you will want to apply processing on the whole group of drum channels. Furthermore, applying a soft compression (i.e. with a low ratio) to the overall mix helps you “glue” all instruments together and constitutes an essential part of any pre-mastering or mastering task. Since most mixes are done in stereo, bus compression has to be done in stereo, too.

1.2 The SOLID BUS COMP

Originally released in the mid-1970s, the analog mixing console that inspired the SOLID MIX SERIES soon became the central element in many of the greatest studios around the world. Claiming to be the mixer behind more platinum selling albums than all other con-

soles combined, this mixing console literally contributed to the sound of the 1980s. The precise and transparent sound of its full-featured channel strips set new references for mixing engineers.

The SOLID BUS COMP brings you the stereo bus compressor of this highly acclaimed mixing desk. This was indeed one of the great benefits of this desk, since it would allow mixing engineers to produce “ear-ready” mixes before sending them to mastering.

Additional Features

Bringing analog hardware into the software world allowed us to add a few great features, which are available in the expert panel of the SOLID BUS COMP. For example, the SOLID BUS COMP offer an additional parallel compression. And, of course, as with any Component in GUITAR RIG, you can save and recall presets for your favorite settings.

2 Using the SOLID BUS COMP

This chapter describes how to use the SOLID BUS COMP.

2.1 Loading the SOLID BUS COMP

Once installed, the SOLID BUS COMP is found in the Component Pool, in the SideKick of GUITAR RIG.

To load the SOLID BUS COMP:

1. Click the [Components](#) button at the top of the SideKick (the left column in GUITAR RIG's window) to display the Component Pool.
2. Find the [Solid Buscomp](#) box in the Pool, whether under the [Dynamics](#) category (if components are currently listed by categories) or under the [SOLID MIX SERIES](#) group (if components are currently listed by products).
3. Double-click the component or drag and drop it onto the Rack to load it.

Sound Settings

Here are a few things you should be aware of when using the SOLID BUS COMP in GUITAR RIG.


- By default the input routing of GUITAR RIG is set to mono. To activate stereo input, switch on the right channel by clicking the [R](#) in the Global Header of GUITAR RIG.
- To make GUITAR RIG plug-in instances receive stereo input by default, start GUITAR RIG as a stand-alone program. Click [Options](#) to open the Options view. In the Options view, click the [Preferences](#) button, then select *Stereo* from the [Default Plugin Input Configuration](#) menu. Close GUITAR RIG. The next time you open a GUITAR RIG plug-in in your host software, it will accept stereo input signals.
- By default GUITAR RIG's gate is enabled. To deactivate the gate, click the [Gate](#) button in the Global Header of GUITAR RIG.



The Global Header in GUITAR RIG.

2.2 SOLID BUS COMP Interface and Controls

This section describes the SOLID BUS COMP interface and controls in detail.



The SOLID BUS COMP user interface.

(1) **THRESHOLD knob:** Adjusts both the threshold level. Turning this knob counter-clockwise will result in more compression.

(2) **MAKEUP knob:** Adjusts the make-up gain. This allows you to offset the overall output level once you have set the desired compression.

(3) **RATIO knob:** Selects the compression ratio. This directly affects how much gain reduction is applied to the input signal. Following ratios are available: 1.5:1 (1.5), 2:1 (2), 3:1 (3), 4:1 (4), 5:1 (4), and 10:1 (10):

- The ratios 3:2 (1.5) to 4:1 (4) generate a soft to moderate compression.
- The ratio 5:1 (5) generates a more severe compression.
- With the ratio 10:1 (10) the compressor tends to behave more like a limiter.



See [↑1.1.1, Main Compression Parameters](#) for more general information on the make-up gain, compression ratio, and threshold level parameters.

(4) **ATTACK knob:** Adjusts the attack time of the compressor, i.e. the time it takes for the compressor to come into full effect once the threshold level has been reached. The attack time is measured in milliseconds. Following attack times are available: 0.1 ms, 0.3 ms, 1 ms, 3 ms, 10 ms, and 30 ms.

(5) **RELEASE knob**: Adjusts the release time of the compressor, i.e. the time it takes for the compressor to get back to its standby state after the signal level has fallen below the threshold level. The release time is measured in seconds. Following release times are available: 0.1 s, 0.2 s, 0.4 s, 0.8 s, and 1.6 s. When the **RELEASE** knob is turned at full right on the **AUTO** position, the release time is set automatically according to the audio content.



See [↑1.1.2, Other Compression Parameters and Features](#) for more general information on the attack and release time.

(6) **COMPRESSION meter**: Allows you to visually monitor the current amount of applied compression in real-time.

SOLID EQ's Expert Controls

The controls found in the expert panel of the SOLID BUS COMP further extend its usability.



To display the controls of the expert panel, click on the small arrow on the right side of the Component.

(7) **DRY and WET sliders**: Allow you to mix the original signal (**DRY** slider) and the compressed signal (**WET** slider). This is called parallel compression (see [↑1.1.2, Other Compression Parameters and Features](#) for more info on this). When the **DRY** slider is set to its left end stop, only the compressed signal is output. Dragging the **DRY** slider to the right progressively blends in the original signal into the compressor output.



After changing the **DRY** slider position, you might have to adjust the **WET** slider accordingly to ensure that the overall output remains at the optimum level!

(8) **SIDECCHAIN button**: Enables/disables the side chain input. The side chain circuitry allows you to feed the compressor's detector with another control signal instead of the input signal itself (see [↑1.1.2, Other Compression Parameters and Features](#) for more info on this). When using GUITAR RIG as a plug-in within your favorite host software, all audio routing is handled by the host. The GUITAR RIG plug-in offers 4 virtual inputs in your host:

- The first two inputs (**In L** and **In R**) are the main inputs.
- The last two inputs (**SideChain L** and **SideChain R**) allow you to route any audio signal to the side chain circuitry.



The way audio routing is handled differs in each host software. For more info on how to route the desired signals to the virtual audio inputs of the GUITAR RIG plug-in, please refer to the documentation of your host software.

(9) LINK L-R button: When this button is off, both left and right input channels are processed separately by the compressor. When this button is on (which is the default setting), their mono sum is used as control signal instead — thus the same compression will be applied to both channels.

(10) Component Preset display and menu: Like in all GUITAR RIG Components, this shows the name of the current Component Preset and allows you to manage the Presets for this Component.



For more info on the Component Presets, please refer to the GUITAR RIG Application Reference.